



DSS Player Pro Release 4 Update Version 4.10.3

Description:

This update (P4UP103EN.EXE) applies to **Release 4.x only** of the DSS Player Pro Dictation and Transcription Modules (Windows 2000/XP/Vista only). To check the current version of your DSS Player Pro software, start your DSS Player Pro application then click on the Help menu→About...

If your application version is not 4.10.3, it is recommended you download and install this software update.

Note: This update will not upgrade DSS Player Pro pre-release 4. For customers who would like to upgrade their DSS Player Pro release 3 software to Release 4 software, please contact your Olympus Authorized Audio Dealer.

Software bugs fixes and/or enhancements:

Software Module	OS	Change	Description
Both	All	Bug	When you select Lotus Notes in the E-mail/FTP option settings, address book entries are not listed in alphabetical order.
Both	All	Bug	When a user marks a file as "Priority" then enters a Comment on the same file, the next time the screen refreshes, the Comment is placed on another file.
Both	All	Bug	When Philips LH-9600 is connected to the pc, Device Detector shutdowns.
Both	All	Bug	When a Download Tray folder is set to a network folder and the network is not available, the message "Download Completed!" appears erroneously after several error messages during download.
TM	All	Bug	Disabled hotkeys (Ctrl+6, Ctrl+7, Ctrl+8, Ctrl+9) registration because these keys conflict with Microsoft word shortcuts.
TM	All	Bug	When multiple transcriptionists share a pool of dictation and the TM is programmed to automatically select the next file, the TM will display the message "file is currently being typed" box. After you click OK, another message displays "Filename abcd0123.dss is not found". The Transcription Module closes after you click OK and will not re-open it without a restart.

Installation Instructions:

NOTE: It is recommended that you logon to the PC as an administrator when installing this software update.

1. Click the **DSS Player Pro Release 4.x Update Version 4.10.3** link to start the download.



3500 CORPORATE Parkway
Center Valley, PA 18034
DIGITAL TECHNICAL SUPPORT
CONSUMER PRODUCTS GROUP
(888) 553-4448
<http://support.olympusamerica.com>

2. Save the file to your hard disk.
3. Close all open programs.
4. Double-click the P4UP103EN.EXE program file on your hard disk to start the update program.
5. Follow the instructions on the screen to complete the installation.